


Installing Caseware Electronic Licencing Version on a Server

The 'Network Licence Server' is used to host licences on a server which will then assign licences to the users connected to the server directly via remote connection.


The 'Network License Server' can also provide Licences to users that have Caseware installed on their local machines as long as they are connected to the server that holds the Licences.


Install the Caseware 'Network Licence Server' found within the Caseware Working Papers program link.



Install the 'Network Licence Server' on the central server that is accessible by all local user machines or hosted application servers.





Proceed through the Install Shield wizard in order to Install the Sentinel RMS Licence Manager 8.5.5 as shown below.










Sentinel RMS License Manager 8.5.5 - InstallShield Wizard



System Firewall Settings Need To Be Modified

The setup program will install the Sentinel RMS License Manager (license server) on this system. To allow communication between the RMS License Manager and the clients running licensed applications, the system firewall settings need to be modified. The Sentinel RMS License Manager will be added to the firewall blocking exceptions list.

Keep the checkbox below selected to unblock the firewall. Clearing this checkbox will let the firewall block the communication between the clients and the RMS License Manager.

Unblock the system firewall for the Sentinel RMS License Manager


Tip: For instructions on unblocking the firewall later, refer to the Sentinel RMS SDK System Administrator's Help.

< Back Next > Cancel

Sentinel RMS License Manager 8.5.5 - InstallShield Wizard

Ready to Install the Program

The wizard is ready to perform selected operation.





Click Install to begin the installation.

If you want to review or change any of your installation settings, click Back. Click Cancel to exit the wizard.

InstallShield


< Back Install Cancel





Click on START, CaseWare International and Get Locking Code

Alternatively access the file directly in file explorer under
C:\ProgramData\Microsoft\Windows\Start Menu\Programs\Caseware International\License
Server.



Email a screen shot of the locking code to Sales@caseware.co.uk



Sales will return an authorisation code to Licence the software once the locking code is received.

Once an authorisation code is received apply this to the server.


In order to apply the Licence to the server access the "Licence Manager"



Click on start all Programs Caseware international then click on "Licence Manager"

(Program Files (x86)\CaseWare International\Licence Administration\WlmAdmin.exe)



Expand the subnet server section and right click on the server the Licence is to be applied to. Add the licence by selecting 'Add feature' - 'From a string' - 'To server and its file' as shown below.





Install Caseware Working Paper program and templates from the Program Package PO*.

When you open the Caseware Working Papers Program you will be prompted to Register Now...

CaseWare Working Papers



CASEWARE 2019
WORKING PAPERS

Version 2019.00.131 (Unregistered) (64-bit)
May 18 2019 02:12:19 [C-*1WXL YUPUZDF9FN2]

There are 5 days remaining until the software expires.


Continue

Register Now...

Patent No. 8,595,381 B2

Copyright CaseWare International Inc. ©2019

Select Caseware Network License server, select the server from the drop down list then click on ok.



To confirm the Licence has been applied open Caseware Working Papers and select file – Licencing as shown below

The Licencing dialogue will appear showing the Licence information for the Licence that is in use from the Licence manager on the server with the number of days available for the license applied.

